

Sony PDZK-MA2 v2.1 Mac OS X Install Guide

October 2012

The Sony PDZK-MA2 v2.1 installer package will allow you to install the plug-ins required for XDCAM EX and XDCAM support within the Avid Media Access feature.

A system that contains multiple Avid applications will only require one installation of the Sony PDZK-MA2 v2.1 plug-in.

Supported Products

The Sony PDZK-MA2 v2.1 plug-in supports the following Avid products:


- Avid Media Composer v6.0.x/v6.5.x
- Avid Symphony v6.0.x/v6.5.x

Please note to always uninstall Sony PDZK-MA2 prior to uninstalling Avid, and then reinstall the Sony PDZK-MA2 v2.1 plug-in after reinstalling Avid products. When installing Avid for the first time, always install all Avid products first and then install the Sony PDZK-MA2 v2.1 plug-in afterwards.

Installation Instructions

Close all Avid applications before running the Sony PDZK-MA2 v2.1 installer.


1. Download the *"Sony_PDZK-MA2_Installer_v2.1.dmg"* installer onto the local system.
2. Double click the file *"Sony_PDZK-MA2_Installer_v2.1.dmg"*.
3. A removable disk called *"Sony_PDZK-MA2_Installer_v2.1"* will mount on the desktop and open automatically.
4. The removable disk contains two files, *"pdzkma2pluginv21mediacomposer6xx.pkg"* and *"pdzkma2pluginv21symphony6xx.pkg"*.




Name	Size	Kind
pdzkma2pluginv21mediacomposer6xx.pkg	1.2 MB	Installer package
pdzkma2pluginv21symphony6xx.pkg	1.2 MB	Installer package

- a. For Avid Media Composer users, run the installer *"pdzkma2pluginv21mediacomposer6xx.pkg"*
- b. For Avid Symphony users, run the installer *"pdzkma2pluginv21symphony6xx.pkg"*
- c. If both Avid Media Composer and Avid Symphony are installed, then either installer may be used. Only one of the installers must be run to install the plug-ins for both products.

5. The installer will appear.
6. Select the Continue button.




7. On the next page select Continue and then Agree to accept the terms of the End-User License Agreement.



- On the Select a Destination page, select “Install for all users of this computer” and then press Continue.




- Press the Install button to begin installation.



- Enter the User Name and Password. This must be a user with administrative privileges.



11. When the install is finished press the Close button.



Uninstall* Instructions for Avid Media Composer and Avid Symphony

To uninstall the Sony PDZK-MA2 v2.1 plug-ins for Avid Media Composer follow the steps listed below. Uninstalling Avid Media Composer and Avid Symphony will not remove the plug-ins installed with PDZK-MA2 v2.1. To remove all the plug-ins installed by the Sony PDZK-MA2 v2.1 please refer to the steps below.

1. Navigate to <SYSTEM DRIVE>\Library\Application Support\Avid\AVX2_Plug-ins\AMA\
2. Delete the *MVP_SonyXDCAMEX.avx*, *MSP_SonyXDCAMEXMP4.avx*, and *SonyXDCAM.avx* files.
3. Empty the Trash to completely erase the files from the system.

*Note that by uninstalling/removing the Sony PDZK-MA2 plug-ins from the system, Avid Media Composer and Avid Symphony will no longer be able to access Sony XDCAM EX and Sony XDCAM media imported via the Link to AMA function.